

Investintech.com Inc. Software Development Kit: PDF-to-Text Function Library User's Guide

July 13, 2007
<http://www.investintech.com>

Copyright 2007 Investintech.com, Inc. All rights reserved

Adobe® is registered by Adobe Systems Incorporated
Acrobat® is registered by Adobe Systems Incorporated
Postscript® is registered by Adobe Systems Incorporated
Access™ is registered by Microsoft Corporation
Excel® is registered by Microsoft Corporation
Visual Basic® is registered by Microsoft Corporation
Visual C++® is registered by Microsoft Corporation
Visual C#® is registered by Microsoft Corporation
Visual J#® is registered by Microsoft Corporation
Visual Studio® is registered by Microsoft Corporation
Win32® is registered by Microsoft Corporation
Windows® is registered by Microsoft Corporation
Windows NT® is registered by Microsoft Corporation
Windows Vista™ is registered by Microsoft Corporation

Contents

Preface	1
About This Documentation	1
Typographical Conventions Used in This Document	1
Getting More Information	1
Customer Service and Technical Support	2
Fax and Mailing Address.....	2
Investintech PDF-to-Text Conversion DLL	3
What is the Investintech PDF-to-Text Conversion DLL?.....	4
Installation Instructions for PDF-to-Text DLL	4
System Requirements	4
Starting the Installation.....	4
Using the Investintech PDF-to-Text Conversion DLL in Microsoft Visual C++ .NET 2003	11
Implicit Linking	11
Linking .lib file with project	12
Using methods from DLL file.....	13
Investintech PDF-to-Text Conversion DLL Methods.....	13
Interface	13
Parameter Type.....	14
File Names	14
Error Handling.....	14
Common Sample Source Code.....	15
Conversion from PDF document to Text	15
PDF_to_Text_CBR	15
Prototype	15
Description	15
Calling Convention	15
Parameters.....	16
Returns	16
Example	16
PDF_to_Text_CBT.....	16
Prototype	16
Description	16
Calling Convention	16
Parameters.....	16
Returns	16
Example	16
PDF_to_Text_CLR.....	17
Prototype	17
Description	17
Calling Convention	17
Parameters.....	17
Returns	17
Example	17
PDF_to_Text_CLT	17
Prototype	17
Description	18

Calling Convention.....	18
Parameters.....	18
Returns.....	18
Example	18
PDF_to_Text_SBR	18
Prototype.....	18
Description.....	18
Calling Convention.....	18
Parameters.....	19
Returns	19
Example	19
PDF_to_Text_SBT.....	19
Prototype.....	19
Description.....	19
Calling Convention.....	19
Parameters.....	19
Returns	19
Example	19
PDF_to_Text_SLR.....	20
Prototype.....	20
Description.....	20
Calling Convention.....	20
Parameters.....	20
Returns	20
Example	20
PDF_to_Text_SLT.....	20
Prototype	20
Description.....	21
Calling Convention.....	21
Parameters.....	21
Returns	21
Example	21
Conversion from PDF document to Text Workbook using a template file	21
PDF_to_Text_Template_CBR.....	21
Prototype.....	21
Description.....	22
Calling Convention.....	22
Parameters.....	22
Returns	22
Example	22
PDF_to_Text_Template_CBT	22
Prototype.....	22
Description.....	22
Calling Convention.....	22
Parameters.....	23
Returns	23
Example	23
PDF_to_Text_Template_CLR	23
Prototype.....	23
Description.....	23
Calling Convention.....	23
Parameters.....	24

Returns	24
Example	24
PDF_to_Text_Template_CLT.....	24
Prototype	24
Description	24
Calling Convention	24
Parameters	24
Returns	25
Example	25
PDF_to_Text_Template_SBR.....	25
Prototype	25
Description	25
Calling Convention	25
Parameters	25
Returns	26
Example	26
PDF_to_Text_Template_SBT.....	26
Prototype	26
Description	26
Calling Convention	26
Parameters	26
Returns	26
Example	26
PDF_to_Text_Template_SLR.....	27
Prototype	27
Description	27
Calling Convention	27
Parameters	27
Returns	27
Example	27
PDF_to_Text_Template_SLT.....	28
Prototype	28
Description	28
Calling Convention	28
Parameters	28
Returns	28
Example	28
Convert from PDF document to CSV file.....	29
PDF_to_CSV_CBR.....	29
Prototype	29
Description	29
Calling Convention	29
Parameters	29
Returns	29
Example	29
PDF_to_CSV_CBT.....	29
Prototype	29
Description	29
Calling Convention	30
Parameters	30
Returns	30
Example	30

PDF_to_CSV_CLR.....	30
Prototype.....	30
Description.....	30
Calling Convention.....	30
Parameters.....	31
Returns.....	31
Example.....	31
PDF_to_CSV_CLT.....	31
Prototype.....	31
Description.....	31
Calling Convention.....	31
Parameters.....	31
Returns.....	31
Example.....	31
PDF_to_CSV_SBR.....	32
Prototype.....	32
Description.....	32
Calling Convention.....	32
Parameters.....	32
Returns.....	32
Example.....	32
PDF_to_CSV_SBT.....	32
Prototype.....	32
Description.....	33
Calling Convention.....	33
Parameters.....	33
Returns.....	33
Example.....	33
PDF_to_CSV_SLR.....	33
Prototype.....	33
Description.....	33
Calling Convention.....	34
Parameters.....	34
Returns.....	34
Example.....	34
PDF_to_CSV_SLT.....	34
Prototype.....	34
Description.....	34
Calling Convention.....	34
Parameters.....	34
Returns.....	34
Example.....	35
Convert from PDF document to CSV file using template file.....	35
PDF_to_CSV_Template_CBR.....	35
Prototype.....	35
Description.....	35
Calling Convention.....	35
Parameters.....	35
Returns.....	36
Example.....	36
PDF_to_CSV_Template_CBT.....	36
Prototype.....	36

Description	36
Calling Convention	36
Parameters	36
Returns	36
Example	36
PDF_to_CSV_Template_CLR	37
Prototype	37
Description	37
Calling Convention	37
Parameters	37
Returns	37
Example	37
PDF_to_CSV_Template_CLT	37
Prototype	37
Description	38
Calling Convention	38
Parameters	38
Returns	38
Example	38
PDF_to_CSV_Template_SBR	38
Prototype	38
Description	39
Calling Convention	39
Parameters	39
Returns	39
Example	39
PDF_to_CSV_Template_SBT	39
Prototype	39
Description	39
Calling Convention	39
Parameters	40
Returns	40
Example	40
PDF_to_CSV_Template_SLR	40
Prototype	40
Description	40
Calling Convention	40
Parameters	41
Returns	41
Example	41
PDF_to_CSV_Template_SLT	41
Prototype	41
Description	41
Calling Convention	41
Parameters	41
Returns	42
Example	42
VB6 callable code	42
PDF_to_Text_VB6	42
Prototype	42
Description	42
Calling Convention	42

Parameters.....	42
Returns.....	43
Example	43
PDF_to_Text_Template_VB6	43
Prototype.....	43
Description.....	43
Calling Convention.....	43
Parameters.....	43
Returns.....	43
Example	43
Prototype.....	44
Description.....	44
Calling Convention.....	44
Parameters.....	44
Returns.....	44
Example	44
PDF_to_CSV_Template_VB6.....	44
Prototype.....	44
Description.....	45
Calling Convention.....	45
Parameters.....	45
Returns.....	45
Example	45
InvestintechConversionDLL_IDString.....	45
Description.....	45
Parameters.....	45
Returns.....	45
Investintech PDF-To-Text Conversion COM Component Methods	46
PDF2Excel	46
Prototype.....	46
Description.....	46
Calling Convention.....	46
Parameters.....	46
Returns.....	46
Example	46
PDF_to_CSV_Template_VB6.....	47
Prototype.....	47
Description.....	47
Calling Convention.....	47
Parameters.....	47
Returns.....	47
Example	47
Index	49

Preface

Welcome to Investintech.com Inc. Software Development Kit (SDK). This SDK provides technologies for converting PDF files into other file. This user's guide provides the basic information needed to use all parts of the SDK. This SDK consists of:

- Investintech PDF To Text Conversion DLL, a Dynamic-Link Library for converting PDF files

This document provides a comprehensive description of the DLL.

About This Documentation

This documentation consists of:

- Investintech PDF To Text Conversion DLL, describing usage and methods of DLL designed to convert PDF files into Text format.

Typographical Conventions Used in This Document

The following table describes typographical and naming conventions used in this document:

Font	Used for	Examples
monospaced	Expected input from the user	a2ecl -pdf2text abc.pdf abc.txt
	Paths and filenames	c:\a2ecl\ a2ecl.exe
	Source code	MessageBox("ABC");
monospaced blue	Source code keywords	If
monospaced green	Source code comments	//this is a comment
monospaced bold	Method name	The AboutBox() method
'Single quoted bold'	Elements of the user interface like buttons, icons etc.	click on 'Start' button, press 'Enter'
blue underlined	Internet links	http://www.investintech.com

Getting More Information

Investintech.com Inc. conducts research in data conversion technology and develops data conversion products utilizing results of the research. More information about our company is available at the company's website <http://www.investintech.com>.

Customer Service and Technical Support

Investintech.com Inc. strives to provide the best possible technical support to its customers and prospective customers. If you would like personal assistance, please feel free to call us or send e-mail to Customer Service or Technical Support. We are available by phone during regular business hours and in the vast majority of cases, we will return our e-mail with an answer the same day it is received.

	<i>Customer Service</i>	<i>Technical Support</i>
Telephone:	+1 416 920 5884	+1 416 920 2539
E-mail:	cs@investintech.com	techsupport@investintech.com
Hours:	Our Business Hours are Monday to Friday 9am-6pm (Eastern Time GMT-5:00).	

Fax and Mailing Address

Mailing Address: Investintech.com Inc.

410-96 Spadina Avenue
Toronto, ON
M5V 2J6 Canada

Fax: +1 416 920 5848

Investintech.com Inc.

Software Development Kit

User's Guide

Investintech PDF-to-Text Conversion DLL

What is the Investintech PDF-to-Text Conversion DLL?

The Investintech PDF-to-Textl Conversion DLL is a collection of methods compiled, linked and stored in a dynamic-link library (DLL) file. These methods provide a set of methods for converting files from PDF to Text format.

Installation Instructions for PDF-to-Text DLL

Below you will find step-by-step instructions to install PDF-to-Text DLL Conversion Librarry on your system. You may want to print this instruction sheet for reference before beginning to install PDF-to-Text DLL.


System Requirements

The minimum computer system resources required to install and use PDF-to-Text DLL are:


- Microsoft Windows XP
- 64 MB of RAM
- 10 MB of available hard disk space
- A software development environment, such as Microsoft Visual Studio or Borland Delphi

Starting the Installation


Start the installation by launching the `InstallPDF2TextDLL.exe` file, e.g. by double clicking it in the Windows Explorer. After that you should see a window that looks like this:



Click the 'Next' button to continue installation. You should see the next window:




Please read the Investintech Software License Agreement carefully and thoroughly. If you wish to continue with installation, choose '**I agree with the above terms and conditions**' and click '**Next**'. Otherwise, click '**Exit**' and installation will terminate. If you clicked '**Next**' you should see the next window:




On this screen you can choose the installation directory for the PDF-to-Text DLL software. The default installation folder will be contained in the **Program Files** folder on your system disk. It is possible to change the location of installation folder either by typing its path directly or by clicking the 'Browse...' button. If the destination folder (directory) you have chosen does not exist, the installation program will create it. Click the '**Next**' button to continue the installation.


PDF-to-TextDLL – Investintech Conversion DLL




Clicking the '**Install**' button will start the installation.



The installation will copy the files that comprise PDF-to-Text DLL to the directory you specified earlier. After a very short period of time, usually about 30 seconds, you should see the next window:



This windows describes the distribution of PDF-to-Text DLL being installed. Click ‘Next’ to continue.



When this window appears, the installation process is complete. Click ‘Finish’ to end the installation program.

Using the Investintech PDF-to-Text Conversion DLL in Microsoft Visual C++ .NET 2003

In this section you will learn how to use the Investintech PDF-to-Text Conversion DLL. All pictures and examples from now on will be based on Microsoft Visual C++ .NET 2003.

In order to use methods contained in DLL you have to link an executable file to DLL. Executable file can be either EXE or DLL file. There are two possible ways of linking: implicit and explicit linking. In this documentation implicit linking will be shown.

Implicit Linking

Implicit linking is load-time linking. The following is needed for executables to implicitly link to Investintech Conversion DLL:

- PDF2TextDLL.h, the header file which contains declarations of exported methods
- PDF2TextDLL.lib, an import library used by the linker


- PDF2TextDLL.dll, the Dynamic Link Library file

All these files are provided by Investintech.com Inc.


Linking .lib file with project

Below you will find step-by-step instructions on how to link PDF2TextDLL.lib file with your project.

Start Visual Studio and select ‘File > Open > Project’. Select the project in which you want to use PDF2TextDLL.dll and click ‘OK’. Select ‘Project > Properties’. You should see the window like next one:



Click the ‘Linker’ folder and open ‘Input’ property page. Modify the ‘Additional Dependencies’ property by clicking the ‘...’ button.



The window titled “Additional Dependencies” should open: type PDF2TextDLL.lib and click the ‘OK’ button. Click ‘OK’ to close “Property Pages” window. You have successfully linked PDF2TextDLL.lib with your project.

Using methods from DLL file

After linking with PDF2TextDLL.lib file you can use methods contained in PDF2TextDLL.dll file. Simply include the PDF2TextDLL.h file in all source files that need to use those methods.

Investintech PDF-to-Text Conversion DLL Methods

In this section you will find details about each method such as: prototype; description; calling conventions; parameters; return value; and sample use of the methods.

Interface

The interface of the Investintech PDF2-to-Text Conversion DLL consists of its exposed methods. The interface contains an exposed method for each combination of: calling convention; parameter type; and error handling.

The calling convention is either the “cdecl” calling convention or the “stdcall” calling convention.

The “cdecl” calling convention is normally used for calling C/C++ functions. It is characterized by the following points:

- arguments are passed in order from right to left
- the calling function is responsible for popping the arguments from the stack at the conclusion of function execution
- an underscore character (_) is prefixed to function names
- no case translation is performed on the function name

The “stdcall” calling convention is typically used to call Windows operating system API functions. It is characterized by the following points:

- arguments are passed in order from right to left
- arguments are passed by value, unless a pointer or reference type is passed.
- The called function is responsible for popping its own arguments from the stack.
- an underscore (_) is prefixed to the name. The name is followed by the at sign (@) followed by the number of bytes (in decimal) in the argument list. For instance, the function declared as void foo(int bar) is decorated as follows: _foo@4
- no case-translation is performed on the function name

Parameter Type

The parameter type is either ANSI (C char *) or UNICODE (BSTR).

File Names

Files may be specified by supplying relative or absolute file names. A relative file name is relative to the application default directory containing the application executable file (e.g. “..\\in_parent_dir.pdf”, “in_application_dir.pdf”, “subdir\\in_sub_directory.pdf”). An absolute file name includes the directory path to the file beginning at the top of the directory tree (e.g. “c:\\pdfs\\absolute_file.pdf”).

It is also possible to use UNC notation (e.g. <\\myserver\\public\\file.pdf>) provided your user account has sufficient access permissions.

Error Handling

The error handling strategy is either to throw an exception (part of the C++ throw-catch error handling construct) or return in integer/boolean type result code (the C style error handling strategy).

The Investintech Conversion DLL identifies the characteristics of a function by an encoded suffix. The suffix is defined by the rules:

- C or S - cdecl or stdcall calling convention
- B or L - BSTR or LPST parameter type
- R or T - return error code or throw exception

Common Sample Source Code

All sample code snippets share the following initialization code snippet:

```
//.h file must be included if we want to use conversion methods
#include <afx.h>

#include <afxwin.h>           // MFC core and standard components
#include "PDF2TextDLL.h"

CString str_inputFile = _T("c:\\pdfs\\in.pdf"); //input file name
CString str_templateFile = _T("c:\\pdfs\\template.ta2e");
CString str_outputFile = _T("out.txt"); //output file name

//conversion from CString to BSTR
BSTR bstr_inputFile = str_inputFile.AllocSysString();
BSTR bstr_templateFile = str_templateFile.AllocString();
BSTR bstr_outputFile = str_output.AllocSysString();
```

Conversion from PDF document to Text

The following methods convert a PDF document file to an Text file.

PDF_to_Text_CBR

Prototype

```
bool PDF_to_Text_CBR(BSTR inFile, BSTR outFile)
```

Description

The PDF_to_Text_CBR() method converts the user specified file from PDF to Text format. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “cdecl” calling convention.

Parameters

inFile	Unicode string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	Unicode string containing the absolute or relative filename of the Text file that will contain the result of the conversion.

Returns

true if PDF file is successfully converted to Text, false otherwise.

Example

```
bool ret = PDF_to_Text_CBR(bstr_inputFile, bstr_outputFile);
```

PDF_to_Text_CBT

Prototype

```
bool PDF_to_Text_CBT(BSTR inFile, BSTR outFile)
```

Description

The PDF_to_Text_CBT() method converts the user specified file from PDF to Text format. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “cdecl” calling convention.

Parameters

inFile	Unicode string containing the absolute or relative filename of PDF file that will be converted to Text format.
outFile	Unicode string containing the absolute or relative filename of Text file that will contain the result of conversion.

Returns

true if PDF file is successfully converted to Text, otherwise throws an exception that should be handled by the calling application.

Example

```
try
{
    bool ret = PDF_to_Text_CBT(bstr_inputFile, bstr_outputFile);
}
catch(...)
{
    // TODO: Handle exception
}
```

PDF_to_Text_CLR***Prototype***

```
bool PDF_to_Text_CLR(LPSTR inFile, LPSTR outFile)
```

Description

The PDF_to_Text_CLR() method converts the user specified file from PDF to Text format. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “cdecl” calling convention.

Parameters

inFile ANSI string containing the absolute or relative filename of the PDF file that will be converted to Text format.

outFile ANSI string containing the absolute or relative filename of the Text file that will contain the result of conversion.

Returns

true if PDF file is successfully converted to Text format, false otherwise.

Example

```
bool ret = PDF_to_Text_CLR(str_inputFile.GetBuffer(), str_outputFile.GetBuffer());
```

PDF_to_Text_CLT

Prototype

```
bool PDF_to_Text_CLT(LPSTR inFile, LPSTR outFile)
```

Description

The `PDF_to_Text_CLT()` method converts the user specified file from PDF to Text format. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “cdecl” calling convention.

Parameters

inFile ANSI string containing the absolute or relative filename of the PDF file that will be converted to Text format.

outFile ANSI string containing the absolute or relative filename of the Text file that will contain the result of conversion.

Returns

true if PDF file is successfully converted to Text format, otherwise throws an exception that the calling application should handle.

Example

```
try
```

```

{
    bool ret = PDF_to_Text_CLT(str_inputFile.GetBuffer(), str_outputFile.GetBuffer());
}
catch(...)
{
    // TODO: Handle exception
}

```

PDF_to_Text_SBR

Prototype

UINT PDF_to_Text_SBR(BSTR inFile, BSTR outFile)

Description

The PDF_to_Text_SBR() method converts the user specified file from PDF to Text format. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

inFile	Unicode string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	Unicode string containing the absolute or relative filename of the Text file that will contain the result of conversion.

Returns

Non-zero integer value if PDF file is successfully converted to Text format, zero integer value otherwise.

Example

```
UINT ret = PDF_to_Text_SBR(bstr_inputFile, bstr_outputFile);
```

PDF_to_Text_SBT

Prototype

```
UINT PDF_to_Text_SBT(BSTR inFile, BSTR outFile)
```

Description

The PDF_to_Text_SBT() method converts the user specified file from PDF to Text format. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

inFile	Unicode string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	Unicode string containing the absolute or relative filename of the Text file that will contain the result of conversion.

Returns

Non-zero integer value if PDF file is successfully converted to Text, otherwise throws an exception that the calling application should handle.

Example

```
try
{
    UINT ret = PDF_to_Text_SBT(bstr_inputFile, bstr_outputFile);
}
catch(...)
{
    // TODO: Handle exception
}
```

PDF_to_Text_SLR

Prototype

```
UINT PDF_to_Text_SLR(LPSTR inFile, LPSTR outFile)
```

Description

The PDF_to_Text_SLR() method converts the user specified file from PDF to Microsoft Text 2.1 format. Any version of Microsoft Text can open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

- | | |
|----------------|--|
| inFile | ANSI string containing the absolute or relative filename of the PDF file that will be converted to XLS format. |
| outFile | ANSI string containing the absolute or relative filename of the Text file containing the result of conversion. |

Returns

Non-zero integer value if PDF file is successfully converted to Text, zero integer value otherwise.

Example

```
UINT retCode = PDF_to_Text_SLR(str_inputFile, str_outputFile);
```

PDF_to_Text_SLT

Prototype

```
UINT PDF_to_Text_SLT(LPSTR inFile, LPSTR outFile)
```

Description

The PDF_to_Text_SLT() method converts the user specified file from PDF to Text format. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

- | | |
|---------------|---|
| inFile | ANSI string containing absolute or relative filename of the PDF file that will be converted to Text format. |
|---------------|---|

outFile ANSI string containing the absolute or relative filename of the Text file that will contain the result of conversion.

Returns

Non-zero integer value if PDF file is successfully converted to Text; otherwise.throws an exception that should be handled by the calling application.

Example

```
try
{
    UINT retCode = PDF_to_Text_SLT(str_inputFile, str_outputFile);
}
catch(...)
{
    //TODO: handle error
}
```

Conversion from PDF document to Text file using a template file

The following methods convert a PDF document file to a Text file using a template file to describe column positions in the PDF file.

PDF_to_Text_Template_CBR

Prototype

```
bool PDF_to_Text_Template_CBR(BSTR inFile, BSTR outFile, BSTR
templateFile)
```

Description

The PDF_to_Text_Template_CBR() method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “cdecl” calling convention.

Parameters

- inFile** Unicode string containing the absolute or relative filename of the PDF file that will be converted to Text format.
- outFile** Unicode string containing the absolute or relative filename of the Text file that will contain the result of conversion.
- templateFile** Unicode string containing the absolute or relative filename of the template file used to parse the PDF file.

Returns

true if PDF file is successfully converted to Text format, false otherwise.

Example

```
bool ret = PDF_to_Text_Template_CBR(str_inputFile, str_outputFile, str_templateFile);
```

PDF_to_Text_Template_CBT**Prototype**

```
bool PDF_to_Text_Template_CBT(BSTR inFile, BSTR outFile, BSTR templateFile)
```

Description

The PDF_to_Text_Template_CBT() method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “cdecl” calling convention.

Parameters

- inFile** Unicode string containing the absolute or relative filename of the PDF file that will be converted to Text format.
- outFile** Unicode string containing the absolute or relative filename of the Text file that will contain the result of conversion.
- templateFile** Unicode string containing the absolute or relative filename of the template file used to parse the PDF file.

Returns

true if PDF file is successfully converted to XLS, otherwise throws an exception that should be handled by the calling application.

Example

```
try
{
    bool ret = PDF_to_Text_Template_CBT(str_inputFile, str_outputFile, str_templateFile);
}
catch(...)
{
    //TODO: handle error
}
```

PDF_to_Text_Template_CLR

Prototype

```
bool PDF_to_Text_Template_CLR(LPSTR inFile, LPSTR outFile, LPSTR templateFile)
```

Description

The PDF_to_Text_Template_CLR() method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “cdecl” calling convention.

Parameters

inFile	ANSI string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	ANSI string containing the absolute or relative filename of the Text file that will contain the result of conversion.
templateFile	ANSI string containing the absolute or relative filename of the template file used to parse the PDF file.

Returns

true if PDF file is successfully converted to Text, false otherwise.

Example

```
bool ret = PDF_to_Text_Template_CLR(str_inputFile, str_outputFile, str_templateFile);
```

PDF_to_Text_Template_CLT**Prototype**

```
bool PDF_to_Text_Template_CLT(LPSTR inFile, LPSTR outFile, LPSTR templateFile)
```

Description

The PDF_to_Text_Template_CLT() method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. Any version of Microsoft Text can open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “cdecl” calling convention.

Parameters

inFile	ANSI string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	ANSI string containing the absolute or relative filename of the Text file that will contain the result of conversion.
templateFile	ANSI string containing the absolute or relative filename of the template file used to parse the PDF file.

Returns

true if PDF file is successfully converted to Text, otherwise throws an exception that should be handled by the calling application.

Example

```
try
{
    bool ret = PDF_to_Text_Template_CLT(str_inputFile, str_outputFile, str_templateFile);
```

```
}
```

```
catch(...)
```

```
{
```

```
    //TODO: handle error
```

```
}
```

PDF_to_Text_Template_SBR

Prototype

```
UINT PDF_to_Text_Template_SBR(BSTR inFile, BSTR outFile, BSTR  
templateFile)
```

Description

The `PDF_to_Text_Template_SBR()` method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

inFile	Unicode string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	Unicode string containing the absolute or relative filename of the Text file that will contain the result of conversion.
templateFile	Unicode string containing the absolute or relative filename of the template file used to parse the PDF file.

Returns

Non-zero integer value if PDF file is successfully converted to text, zero integer value otherwise.

Example

```
UINT ret = PDF_to_Text_Template_SBR(str_inputFile, str_outputFile, str_templateFile);
```

PDF_to_Text_Template_SBT

Prototype

```
UINT PDF_to_Text_Template_SBT(BSTR inFile, BSTR outFile, BSTR
templateFile)
```

Description

The `PDF_to_Text_Template_SBT()` method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

inFile	Unicode string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	Unicode string containing the absolute or relative filename of the Text file that will contain the result of conversion.
templateFile	Unicode string containing the absolute or relative filename of the template file used to parse the PDF file.

Returns

Non-zero integer value if PDF file is successfully converted to Text, otherwise throws an exception that should be handled by the calling application.

Example

```
try
{
    UINT ret = PDF_to_Text_Template_SBT(bstr_inputFile, bstr_outputFile, bstr_templateFile);
}
catch(...)
{
    //TODO: handle error
}
```

PDF_to_Text_Template_SLR

Prototype

```
UINT PDF_to_Text_Template_SLR(LPSTR inFile, LPSTR outFile, LPSTR templateFile)
```

Description

The `PDF_to_Text_Template_SLR()` method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

inFile	ANSI string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	ANSI string containing the absolute or relative filename of the Text file that will contain the result of conversion.
templateFile	Unicode string containing the absolute or relative filename of the template file used to parse the PDF file.

Returns

Non-zero integer value if PDF file is successfully converted to Text, zero integer value otherwise.

Example

```
UINT ret = PDF_to_Text_Template_SLR(str_inputFile, str_outputFile, str_templateFile);
```

PDF_to_Text_Template_SLT

Prototype

```
UINT PDF_to_Text_Template_SLT(LPSTR inFile, LPSTR outFile, LPSTR templateFile)
```

Description

The `PDF_to_Text_Template_SLT()` method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. Any version of Microsoft Text can open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

inFile	ANSI string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	ANSI string containing the absolute or relative filename of the Text file that will contain the result of conversion.
templateFile	ANSI string containing the absolute or relative filename of the template file used to parse the PDF file.

Returns

Non-zero integer value if PDF file is successfully converted to Text, otherwise throws an exception that should be handled by the calling application.

Example

```
try
{
    UINT ret = PDF_to_Text_Template_SLT(str_inputFile, str_outputFile, str_templateFile);
}
catch(...)
{
    //TODO: handle error
}
```

VB6 callable code

VB6 client applications must use these functions in order to avoid runtime errors related to stack and string references.

PDF_to_Text_VB6

Prototype

```
UINT PDF_to_Text_VB6(BSTR inFile, BSTR outFile)
```

Description

The PDF_to_Text_VB6() method converts the user specified file from PDF to Text format. Any version of Microsoft Text can open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

inFile	Unicode string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	Unicode string containing the absolute or relative filename of the Text file that will contain the result of conversion.

Returns

Non-zero integer value if PDF file is successfully converted to Text, zero integer value otherwise.

Example

```
UINT ret = PDF_to_Text_VB6(bstr_inputFile, bstr_outputFile);
```

PDF_to_Text_Template_VB6

Prototype

```
UINT PDF_to_Text_Template_VB6(BSTR inFile, BSTR outFile, BSTR
templateFile)
```

Description

The PDF_to_Text_Template_VB6() method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. Any text editor may be used to open the created output file. The original PDF file is not modified.

Calling Convention

The function uses the “stdcall” calling convention.

Parameters

inFile	Unicode string containing the absolute or relative filename of the PDF file that will be converted to XLS format.
outFile	Unicode string containing the absolute or relative filename of the Text file containing the result of conversion.
templateFile	Unicode string containing the absolute or relative filename of the template file used to parse the PDF file.

Returns

Non-zero integer value if PDF file is successfully converted to Text, zero integer value otherwise.

Example

```
try
{
    UINT ret = PDF_to_Text_Template_VB6(str_inputFile, str_outputFile, str_templateFile);
}
catch(...)
{
    //TODO: handle error
}
```

InvestintechConversionDLL_IDString

```
char* InvestintechConversionDLL_IDString()
```

Description

The **InvestintechConversionDLL_IDString()** method returns vendor's ID string.

Parameters

None.

Returns

"Investintech Conversion DLL Version 1.00 by Investintech.com Inc." string.

Investintech PDF-To-Text Conversion COM Server Methods

This section provides a description of the conversion methods exposed by the PDF-To-Text COM Component. The COM Server defines the CoClass CPDF2Text that implements the interface IPDF2Text. The interface consists of the following methods

PDF2Text

Prototype

```
HRESULT PDF2Text([in] BSTR sourceFileName, [in] BSTR destinationFileName, [out,retval] VARIANT_BOOL *successFlag)
```

Description

The **PDF2Text()** method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. The output file may be opened with a text editor or any version of Microsoft Text. The original PDF file is not modified.

Parameters

inFile	Unicode string containing the absolute or relative filename of the PDF file that will be converted to Text format.
outFile	Unicode string containing the absolute or relative filename of the Text file that will contain the result of conversion.
SuccessFlag	Pointer to boolean variable that will contain the result of the operation: true is the conversion operation is successful; else false.

Returns

Non-zero integer value if PDF file is successfully converted to Text, zero integer value otherwise.

Example

```
HRESULT result = PDF2Text(bstr_inputFile, bstr_outputFile, bstr_templateFile);
```

TemplatePDF2Text**Prototype**

```
HRESULT TemplatePDF2Text([in] BSTR inFile, [in] BSTR outFile,
[in] BSTR templateFile, PDF2Text[out,retval] VARIANT_BOOL
*successFlag)
```

Description

The TemplatePDF2Text() method converts the user specified file from PDF to Text format. It uses the column positions described in the template file to convert data on the PDF file. The output file may be opened with a text editor. The original PDF file is not modified.

Parameters

inFile	Unicode string containing the absolute or relative filename of the PDF file that will be converted to CSV format.
outFile	Unicode string containing the absolute or relative filename of the Text file that will contain the result of conversion.
templateFile	Unicode string containing the absolute or relative filename of the template file used to parse the PDF file.

SuccessFlag Pointer to boolean variable that will contain the result of the operation: true is the conversion operation is successful; else false.

Returns

HRESULT enumerated value indicating the result of the COM operation.

Example

```
HRESULT result = TemplatePDF2Text (bstr_inputFile, bstr_outputFile, bstr_templateFile,  
&boolFlag);
```

Index

A	
Able2Extract Command Line	
Installation Instructions	4
System Requirements	4
C	
Conversion DLL	3
Customer Service	2
I	
Investintech.com Inc.	1
InvestintechSDK DLL	4
Implicit Linking	11
InvestintechSDK_IDString	45
InvestintechSDK_PDF_to_Text	15, 16, 17, 29, 30, 31, 32, 33, 34, 44
Methods	13, 46
InvestintechSDK.dll	11
InvestintechSDK.h	11
InvestintechSDK.lib	11
T	
Technical Support	2

ERROR: undefined
OFFENDING COMMAND: ceo

STACK:

/Ref_part3
/Dest
-mark-